

How to make selections

While in the Editor in Adobe Photoshop Elements, you can select an entire image or isolated parts of an image for editing. To select the entire image, use the commands in the Select menu. For more precise selections, you can choose from several selection tools in the Tools palette (**Figure 1**).

When you make a selection, a border identifies which parts of the image are selected. You can refine a selection by adding to it, subtracting from it, expanding it, contracting it, or moving it. You can also hide the selection border to see the effects of your edits more clearly.

Selection tools




Figure 1 Selection tools

Rectangular Marquee: Draws square or rectangular selection borders.

Elliptical Marquee: Draws round or elliptical selection borders.

Lasso: Draws freehand selection borders. This tool is great for making very precise selections.

Magnetic Lasso: Draws a selection border that snaps to edges you drag over in a photo.

Polygonal Lasso: Draws multiple straight-edged segments of a selection border. Use this tool to surround an area with perfectly straight segments.

Magic Wand: Selects pixels of similar color with one click.

Quick Selection: Automatically makes a selection based on color and texture similarity when you draw, scribble, or click the area you want to select.

Selection Brush: Selects the area on which you paint.

Selecting an entire image

Sometimes all you need to do is select an entire photo or all the contents of a single layer. Choose **Select > Select All**. When you choose **Select All**, the entire canvas area is selected, and changes apply to the entire canvas area for whichever layer is currently selected. Use the **Select All** command to copy the entire contents of one layer to another layer or to another file, or for applying special effects, such as filters.

You can also use the **Select** menu to deselect, reselect, or hide a selection.

For the step-by-step instructions in this guide, open the Editor and select **Full** from the **Edit** tab to work in the **Standard Edit** workspace.

To select and deselect all the contents of a layer by using commands:

1. In the **Layers** palette, click the layer you want to work with.
2. Choose **Select > All**.

The selection border, sometimes referred to as *marching ants*, shows you have selected the entire canvas for the active layer. You can now cut, copy, or apply edits to the selected area (**Figure 2**).

3. To remove the selection, choose **Select > Deselect**.
4. To repeat the most recent selection, choose **Select > Reselect**.

The selection border reappears.

Note: Sometimes the selection border can make it difficult to see what you are editing. You can turn off the selection border while maintaining the selection by pressing **Ctrl+H** (Windows) or **Command+H** (Mac OS). Press **Ctrl+H** (Windows) or **Command+H** (Mac OS) a second time to show the selection.

Be careful when hiding a selection. Accidentally deleting parts of an image or applying an effect unintentionally is very easy when the selection border is hidden. It is best to briefly hide the selection to see what you need to see, and then turn it back on right away.




Figure 2 Entire image selected

Using the marquee tools

The Rectangular Marquee tool draws square or rectangular selection borders, and the Elliptical Marquee tool draws round or elliptical selection borders (**Figure 3**).




Figure 3 Marquee tools

To select rectangular or elliptical areas:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select either the Rectangular Marquee tool or the Elliptical Marquee tool.
3. Select a mode for the tool in the options bar (**Figure 4**).




Figure 4 Marquee selection modes

Normal: Drag to control the size of the selection.

Fixed Aspect Ratio: Control the proportions of the selection by using the Width and Height boxes.

Fixed Size: Set a specific size for the selection area by typing values in the Width and Height boxes.

Note: You can also feather the selection, which softens the border of the selected area.

4. Drag over the area you want to select (**Figure 5**).

Note: With the marquee tool still selected, you can drag the selected area to a new position in the image. This moves the selection border but not the selected piece of the image. To move the selected piece of the image, change to the Move tool before dragging the selection.




Figure 5 Elliptical marquee selection

Modifying selections

Making selections in Photoshop Elements can be a trial-and-error process for even the most experienced photo editors. Fortunately, Photoshop Elements provides several options for adjusting your selections. You may have noticed the small square buttons in the options bar when a selection tool is active (**Figure 6**). These buttons control how a selection tool functions, whether to start a new selection with each click or to add or subtract from the current selection area. They are available for all of the selection tools except the Selection Brush tool and Quick Selection tool, which have their own set of options.




Figure 6 Selection options

New Selection: Replaces the current selection with a new selection when you click and drag. With this option selected, dragging within the selection adjusts the position of the selection over the image.

Add To Selection: Adds to the existing selection wherever you drag.

Subtract From Selection: Removes from the existing selection wherever you drag.

Intersect With Selection: Selects the part of the existing selection that overlaps wherever you drag.

You can also modify the current selection by using the Modify commands on the Select menu (**Figure 7**). For example, you can expand or contract a selection by a fixed number of pixels. You can select the inverse of the current selection. For example, you might select an area you want to preserve and then select the inverse (everything else) and delete it.




Figure 7 Modify submenu

After making a complex selection, you may also want to save it. After saving a selection, you can easily reload it from the Select menu.

To add or subtract from a selection:

1. In the Editor, choose a selection tool and select an area of the image (**Figure 8**).
2. To add to the selection, click the Add To Selection button in the options bar and drag an area to add it to the selection.

The selection border expands to include the area you added (**Figure 9**).

Note: If you drag across the current selection border, the old and new selections blend together to form a larger selection. You can also drag to add a new selection border that is separate from the original selection (**Figure 10**).

3. To subtract from the selection, click the Subtract From Selection button in the options bar and drag an area to remove it from the selection.



Figure 8 First selection




Figure 9 Add to expand the selection




Figure 10 Add a separate selection

To create a selection from an intersection:

1. In the Editor, choose a selection tool and select an area of the image (**Figure 11**).
2. Click the Intersect With Selection button in the options bar and drag an overlapping area to create the intersection (**Figure 12**).

When you release the mouse button, the intersection defines the final selection (**Figure 13**).




Figure 11 First selection




Figure 12 Drag to create the intersection




Figure 13 Final selection

To expand and contract selections:

1. In the Editor, choose a selection tool and select an area of the image.
2. Choose Select > Modify > Expand or Select > Modify > Contract.

The Expand (or Contract) Selection dialog box appears (**Figure 14**).

3. Enter a number of pixels between 1 and 100.
4. Click OK.
The selection border expands or contracts by the number of pixels you specified.



Figure 14 Expand Selection dialog box

To save a selection:

1. In the Editor, use one or more selection tools to define a selection.
2. Choose Select > Save Selection.

The Save Selection dialog box appears (**Figure 15**).

3. Enter a name for the selection and click OK.




Figure 15 Save Selection dialog box

To load a saved selection:

1. Choose Select > Load Selection.
The Load Selection dialog box appears.
2. Select a selection to load from the Selection menu (**Figure 16**).

3. Click OK.
The selection border appears.




Figure 16 Load Selection dialog box

Moving a selection

After you make a selection, you can move the entire selection to another part of the image. This can create interesting effects, especially with photo collages and other projects that use parts of photos. You can also move selections to adjust the location of an object in the image. By default, when you move a selection, it is removed from its original position. When you hold down the ALT key and move a selection, Photoshop Elements moves a copy of the selection, leaving the original intact.

To move a selection:

1. Make a selection by using the Rectangular Marquee tool, the Elliptical Marquee tool, or another selection tool.
The border of the selection changes to transform handles.
2. Click the Move tool in the Toolbar.
The border of the selection changes to transform handles.
3. Drag the selection to another position (**Figure 17**).
4. Choose Edit > Undo Duplicate to return the selection to its original position.
5. Hold down the ALT key and drag the selection again.
Photoshop Elements makes a duplicate of the selection.




Figure 17 Moving a selection




Figure 18 Copying a selection

Putting a border on a selection

You can add a border to any selection by using the Stroke command.

To add a border to a selection:

1. Make a selection by using the Rectangular Marquee tool, the Elliptical Marquee tool, or another selection tool.
2. Choose Edit > Stroke (Outline) Selection.
The Stroke dialog box opens (**Figure 19**).
3. Enter values for the following stroke options.
 - *Width*: Enter a width in pixels.
 - *Color*: Click on the color box to open a color selector.
 - *Location*: Choose Inside, Center, or Outside to determine where the stroke appears in relation to the selection.
 - *Blending*: Blending determines how the stroke color blends with the background (if at all). Leave this at Normal for no blending.
 - *Opacity*: Reduce this number from 100% to make the stroke transparent.
4. Click OK.
The border appears around the selection (**Figure 20**).




Figure 19 Stroke dialog box



Figure 20 Stroke applied to selection

Changing the color of a selection

1. Make a selection by using the Rectangular Marquee tool, the Elliptical Marquee tool, or another selection tool.

2. Choose Edit > Fill Selection.

The Fill Layer dialog box opens.

3. Choose a color for the fill.

By default, the fill will match the foreground color currently selected in the Toolbar. You can also choose the background color, use the Color Picker to choose a color, use a pattern, or directly choose black, white, or grey.

4. Choose whether to blend the fill with the background.

Leave Blending at Normal for no blending.

5. Reduce the value of Opacity to make the fill transparent.

When the Opacity is set at 100%, the fill is solid.

6. Click OK.

The color of the selection changes (**Figure 22**).




Figure 21 Fill Layer dialog box



Figure 22 Fill applied (Opacity at 50%)

Using the Quick Selection tool and the Selection Brush tool

Use the Quick Selection tool to “paint” a selection quickly with an adjustable round brush tip. As you drag, the selection expands outward, finding and following defined edges in the image. The marks you make don’t need to be precise because Photoshop Elements draws the selection border for you automatically.

The Selection Brush tool selects whatever you paint. Use the Selection Brush to clean up a selection if the Quick Selection tool doesn’t produce the exact results you’re looking for.

When using the Quick Selection tool to identify a selection area, you can create a new selection, add to the existing selection, or subtract from the existing selection by using the buttons in the options bar (**Figure 23**).




Figure 23 Quick Selection options

Use the Brush picker in the options bar to set the size and shape of the Quick Selection tool. Select the All Layers option if you want the selection to apply to all layers instead of only the layer currently selected in the Layers palette. Select the Auto-Enhance option to reduce roughness and “blockiness” in the selection boundary. Click the Refine Edge button to make adjustments to an existing selection.

To select an area by using the Quick Selection tool:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select the Quick Selection tool.
3. Open the Brush picker (**Figure 24**) to change the brush tip size of the Quick Selection tool. Type a pixel size or move the Diameter slider. Use the Size pop-up menu options to make the brush tip size sensitive to pen pressure or a stylus wheel.
4. Click or drag inside the part of the image you want to select. (**Figure 25**).

The selection grows as you paint. As you paint near the edges of a shape, the selection area extends to follow the contours of the shape edge.

If the selection isn't perfect, you can try again or use the Add To Selection and Subtract From Selection options to refine the selection.

5. Click the Refine Edge button to improve the quality of a selection's edges and view the selection against a different background for easy editing.

The Refine Edge dialog box opens (**Figure 26**):

Smooth: Reduces irregular areas (“hills and valleys”) in the selection boundary, creating a smoother outline. Move the slider or type a value from 0 to 100.

Feather: Creates a soft-edged transition between the selection and its surrounding pixels. Move the slider or type a value from 0 to 250 pixels to define the width of the feathered edge.

Contract/Expand: Shrinks or enlarges the selection boundary. Move the slider or type a value from 0 to 100% to expand the selection, or from 0 to -100% to contract the selection. This option is most useful for making subtle adjustments to soft-edged selections. Shrinking the selection can help remove unwanted background colors from selection edges.




Figure 24 Brush picker for the Quick Selection tool




Figure 25 Using the Quick Selection tool




Figure 26 Refine Edge dialog box

To refine a selection by using the Selection Brush tool:

1. Change to the Selection Brush tool.
2. In the options bar, click either Add To Selection or Subtract From Selection (**Figure 27**).
3. In the options bar, select a size for the brush.



Figure 27 Selection Brush options

Note: You can also determine hardness for the brush, as well as choose to make the selection a mask. For more information on masks, see “Edit layer masks” in Photoshop Elements online help.

4. Drag to paint the areas you want to add to or subtract from the selection.

Note: Zooming in may help you to refine a selection. To use the Zoom tool, choose View > Zoom In, or press Ctrl+= (Windows) or Command+= (Mac OS).

Using the Magic Wand tool

You can use the Magic Wand tool to select any part of an image with a similar color range. For example, if the image contains a large area of similar color, such as a blue sky, the Magic Wand tool can make selecting this large area very simple.

When using the Magic Wand tool, you can modify its behavior by using the settings in the options bar (**Figure 28**).



Figure 28 Magic Wand options

Tolerance: A low tolerance selects colors very similar to the pixel on which you click. A higher number selects a wider range of colors. Type a number from 0 to 255.

Anti-alias: Produces a smooth selection edge.

Contiguous: Selects only pixels that are adjacent to each other. With this option deselected, pixels with a similar color throughout the image will be selected.

All Layers: Bases selection on colors in all the visible layers. With this option deselected, the selection will be based on colors in the active layer only.

Once you begin your selection, you can add to the selection by holding down Shift as you click. You can subtract from the selection by holding down Alt (Windows) or Option (Mac OS) as you click.

To make selections based on color:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select the Magic Wand tool.
3. Select options for the Magic Wand tool in the options bar.
4. Click in the image to select an area of one color(**Figure 29**).
5. If necessary, add to or subtract from the selection by holding down Shift as you click.

In this example, the first click selected the middle stripe on the sleeve. To add to the selection, Shift was pressed while clicking the second color in the jacket(**Figure 30**).




Figure 29 Define the color for the selection with a click




Figure 30 Add to the selection with a Shift-click

Using the lasso tools

To make very precise selections that contain a range of colors, use the lasso tools (**Figure 31**). The basic Lasso tool lets you draw a freehand line around an area to define the selection border. The area can be any shape or size. When the two ends of the line meet, the selection is complete.

If freehand drawing is too challenging, you can use the Polygonal Lasso tool. The Polygonal Lasso tool draws straight-edged segments each time you click. You can add as many segments as needed to surround the selection area. By zooming in and placing lots of very short segments together, you can create a selection border that appears to be a smooth curve.

If your image includes complex edges set against high-contrast backgrounds, try the Magnetic Lasso tool. The Magnetic Lasso tool draws a selection border that snaps to the edges of objects you drag over in the photo. Your image needs a clearly defined edge with plenty of contrast for this to work well.




Figure 31 Lasso tools

To draw selections with the Lasso tool:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select the Lasso tool.
3. In the options bar, select options for the Lasso tool.
4. Drag to enclose the area you want to select (**Figure 32**).

Note: As you drag, you define the selection area. When the end of your selection returns to where you started, the selection is complete. Go slowly and be patient. If you are not getting the result you want, it may be easier to deselect and start over.



Figure 32 Drawing a selection with the Lasso

To make a selection by using the Polygonal Lasso tool:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select the Polygonal Lasso tool.
3. In the options bar, select options for the Polygonal Lasso tool.
4. Click where you want the first straight segment to begin, and then click again where you want the first segment to end and the next one to begin.
5. Continue clicking to create segments (**Figure 33**).

Note: If you zoom in and create many very short segments, the selection border appears to be smoothly curved.

If you make a mistake, press Delete to erase segments and back up. You can switch from straight-edged segments to a freehand drawing by holding down Alt (Windows) or Option (Mac OS) and dragging.

6. To close the selection, do one of the following:
 - Position the pointer over the starting point and click.
 - If the pointer is not over the starting point, double-click, or Ctrl-click. A straight selection segment is drawn from your pointer to the starting point of your selection.

Note: If you zoomed in, you can zoom back out to see the finished selection.




Figure 33 Selecting with the Polygonal Lasso tool

To make a selection by using the Magnetic Lasso tool:

1. In the Layers palette, click the layer you want to work with.
2. In the Tools palette, select the Magnetic Lasso tool.
3. In the options bar, select options for the Magnetic Lasso tool.
4. Click where you want the first straight segment to begin, and then click again where you want the first segment to end and the next one to begin.
5. Drag along the border of the area that you want to select (**Figure 34**).

The Magic Lasso automatically snaps to the border between the selection and the rest of the image.

If you make a mistake, press Delete to erase segments and return to an earlier state in the process.

6. To close the selection, do one of the following:
 - Position the pointer over the starting point and click.
 - If the pointer is not over the starting point, double-click, or Ctrl-click. A straight selection segment is drawn from your pointer to the starting point of your selection.




Figure 34 Selecting with the Magnetic Lasso tool